

---

# **Rotest Documentation**

***Release 3.2.2***

**gregoil**

**Aug 16, 2018**



---

## Contents

---

<b>1</b>	<b>Basic</b>	<b>1</b>
1.1	Rotest . . . . .	1
1.2	Getting Started . . . . .	3
1.3	Command Line Options . . . . .	11
1.4	Output Handlers . . . . .	19
1.5	Configurations . . . . .	22
<b>2</b>	<b>Advanced</b>	<b>27</b>
2.1	Adding Custom Output Handlers . . . . .	27
2.2	Blocks code architecture . . . . .	29
<b>3</b>	<b>Indices and tables</b>	<b>35</b>



## 1.1 Rotest

Watch the demo

Rotest is a resource oriented testing framework, for writing system or integration tests.

Rotest is based on Python's *unittest* module and on the Django framework. It enables defining simple abstracted components in the system, called resources. The resources may be DUT (devices under test) or they may help the test process. The tests look very much like tests written using the builtin module *unittest*.

### 1.1.1 Why Use Rotest?

- Allowing teams to share resources without interfering with one another.
- Easily abstracting automated components in the system.
- Lots of useful features: multiprocessing, filtering tests, variety of output handlers (and the ability to create custom ones), and much more.

### 1.1.2 Examples

For a complete step-by-step explanation about the framework, you can read our documentation at [Read The Docs](#). If you just want to see how it looks, read further.

For our example, let's look at an example for a `Calculator` resource:

```
import os
import rpyc
from django.db import models
from rotest.management import base_resource
from rotest.management.models import resource_data
```

(continues on next page)

(continued from previous page)

```
class CalculatorData(resource_data.ResourceData):
    class Meta:
        app_label = "resources"

        ip_address = models.IPAddressField()

class Calculator(base_resource.BaseResource):
    DATA_CLASS = CalculatorData

    PORT = 1357
    EXECUTABLE_PATH = os.path.join(os.path.expanduser("~"),
                                    "calc.py")

    def connect(self):
        self._rpyc = rpyc.classic.connect(self.data.ip_address,
                                           self.PORT)

    def calculate(self, expression):
        result = self._rpyc.modules.subprocess.check_output(
            ["python", self.EXECUTABLE_PATH, expression])
        return int(result.strip())

    def finalize(self):
        if self._rpyc is not None:
            self._rpyc.close()
            self._rpyc = None
```

The `CalculatorData` class is a standard Django model that exposes IP address of the calculator machine through the `data` attribute. Also, we're using `rpyc` for automating the access to those machines. Except from that, it's easy to notice how the `connect` method is making the connection to the machine, and how the `finalize` method is cleaning afterwards.

Now, an example for a test:

```
from rotest import main
from rotest.core import TestCase

class SimpleCalculationTest(TestCase):
    calculator = Calculator()

    def test_simple_calculation(self):
        self.assertEqual(self.calculator.calculate("1+2"), 3)

if __name__ == "__main__":
    main()
```

The test may include the `setUp` and `tearDown` methods of *unittest* as well, and it differs only in the request for resources.

Following, those are the options exposed when running the test:

```
$ rotest -h
Run tests in a module or directory.
```

(continues on next page)

(continued from previous page)

```

Usage:
    rotest [<path>...] [options]

Options:
    -h, --help
        Show help message and exit.
    --version
        Print version information and exit.
    -c <path>, --config <path>
        Test configuration file path.
    -s, --save-state
        Enable saving state of resources.
    -d <delta-iterations>, --delta <delta-iterations>
        Enable run of failed tests only - enter the number of times the
        failed tests should be run.
    -p <processes>, --processes <processes>
        Use multiprocess test runner - specify number of worker
        processes to be created.
    -o <outputs>, --outputs <outputs>
        Output handlers separated by comma.
    -f <query>, --filter <query>
        Run only tests that match the filter expression,
        e.g. 'Tag1*' and not Tag13'.
    -n <name>, --name <name>
        Assign a name for current launch.
    -l, --list
        Print the tests hierarchy and quit.
    -F, --failfast
        Stop the run on first failure.
    -D, --debug
        Enter ipdb debug mode upon any test exception.
    -S, --skip-init
        Skip initialization and validation of resources.
    -r <query>, --resources <query>
        Specify resources to request by attributes,
        e.g. '-r res1.group=QA,res2.comment=CI'.

```

## 1.2 Getting Started

Using Rotest is very easy! We'll guide you with a plain and simple tutorial, or you can delve into each step separately.

### 1.2.1 Installation

Installing Rotest is very easy. The recommended way is using pip:

```
$ pip install rotest
```

If you prefer to get the latest features, you can install Rotest from source:

```

$ git clone https://github.com/gregoil/rotest
$ cd rotest
$ python setup.py install

```

## 1.2.2 Basic Usage

In this tutorial you'll learn:

- What are the building blocks of Rotest.
- How to create a Rotest project.
- How to run tests.

### The Building Blocks of Rotest

Rotest is separated into several component types, each performs its specific tasks. Here is a brief explanation of the components:

- `rotest.core.TestCase`: The most basic runnable unit. Just like `unittest.TestCase`, it defines the actions and assertions that should be performed to do the test. For example:

```
from rotest.core import TestCase

class MyCase(TestCase):
    def test_something(self):
        result = some_function()
        self.assertEqual(result, some_value)
```

- `rotest.core.TestSuite`: Again, a known concept from the `unittest` module. It aggregates tests, to make a semantic separation between them. This way, you can hold a bunch of tests and run them as a set. A `rotest.core.TestSuite` can hold each of the following:
  - `rotest.core.TestCase` classes.
  - `rotest.core.TestSuite` classes.
  - The more complex concept of `rotest.core.TestFlow` classes.

```
from rotest.core import TestSuite

class MySuite(TestSuite):
    components = [TestCase1,
                  TestCase2,
                  OtherTestSuite]
```

### Creating a Rotest Project

Rotest has a built in a client-server infrastructure, for a good reason. There must be someone who can distribute resources between tests, that are being run by several developers or testers. Thus, there must be a server that have a database of all the instances. Rotest uses the infrastructure of Django, to define this database, and to make use of the Django's admin frontend to enable changing it.

First, create a Django project, using:

```
$ django-admin startproject rotest_demo
$ cd rotest_demo
```

You'll end up with the following tree:



```

.
├── manage.py
└── rotest_demo
    ├── __init__.py
    ├── settings.py
    ├── urls.py
    └── wsgi.py

```

Inside it, create a file in the root directory of the project called `rotest.yml`, that includes all configuration of Rotest:

```

rotest:
  host: localhost
  django_settings: rotest_demo.settings

```

Pay attention to the following:

- The *rotest* keyword defines its section as the place for Rotest's configuration.
- The *host* key is how the client should contact the server. It's an IP address, or a DNS of the server. For now, both the client and server are running on the same machine., but it doesn't have to be that way.
- The *django\_settings* key is directing to the settings of the Django app, that defines all relevant Django configuration (DB configuration, installed Django applications, and so on).

## Adding Tests

Let's create a test that doesn't require any resource. Create a file named `test_math.py` with the following content:

```

from rotest import main
from rotest.core import TestCase

class AddTest(TestCase):
    def test_add(self):
        self.assertEqual(1 + 1, 2)

if __name__ == "__main__":
    main()

```

That's a very simple test, that asserts integers addition operation in Python. To run it, just do the following:

```

$ python test_math.py
21:46:20 : Test run has started
Tests Run Started
21:46:20 : Test AnonymousSuite_None has started running
Test AnonymousSuite Started
21:46:20 : Running AnonymousSuite_None test-suite
21:46:20 : Test AddTest.test_add_None has started running
Test AddTest.test_add Started
21:46:20 : Finished setUp - Skipping test is now available
21:46:20 : Starting tearDown - Skipping test is unavailable
21:46:20 : Test AddTest.test_add_None ended successfully
Success: test_add (__main__.AddTest)
21:46:20 : Test AddTest.test_add_None has stopped running
Test AddTest.test_add Finished
21:46:20 : Test AnonymousSuite_None has stopped running

```

(continues on next page)

(continued from previous page)

```
Test AnonymousSuite Finished
  21:46:20 : Test run has finished
Tests Run Finished

Ran 1 test in 0.012s

OK
  21:46:20 : Finalizing 'AnonymousSuite' test runner
  21:46:20 : Finalizing test 'AnonymousSuite'
```

Alternatively, you can skip importing and using `rotest.main()`, and use the built-in tests discoverer:

```
$ rotest test_math.py
or
$ rotest <dir to search tests in>
```

### 1.2.3 Using Resources

The true power of Rotest is in its client-server infrastructure, which enables writing resource-oriented tests, running a dedicated server to hold all resources, and enabling clients run tests.

In this tutorial, you'll learn:

- How to create a resource class.
- How to run the server, that acts as a resource manager.
- How to write tests that use resources.

#### Creating a Resource Class

In the root of your project, create a new Django application:

```
$ django-admin startapp resources
```

You'll see a new directory named `resources`, in the following structure:

```
.
├── manage.py
├── resources
│   ├── admin.py
│   ├── __init__.py
│   ├── migrations
│   │   └── __init__.py
│   ├── models.py
│   ├── tests.py
│   └── views.py
├── rotest_demo
│   ├── __init__.py
│   ├── __init__.pyc
│   ├── settings.py
│   ├── settings.pyc
│   ├── urls.py
│   └── wsgi.py
├── rotest.yml
└── test_math.py
```

Don't forget to add the new application as well as `rotest` to the `INSTALLED_APPS` configuration in the `rotest_demo/settings.py` file:

```
...

INSTALLED_APPS = (
    'rotest.core',
    'rotest.management',
    'resources',
    'django.contrib.admin',
    'django.contrib.auth',
    ...
)
```

We're going to write a simple resource of a calculator. Edit the `resources/models.py` file to have the following content:

```
from django.db import models
from rotest.management.models import resource_data

class CalculatorData(resource_data.ResourceData):
    class Meta:
        app_label = "resources"

    ip_address = models.IPAddressField()
```

The `CalculatorData` class is the database definition of the Calculator resource. It defines any characteristics it has, as oppose to behaviour it may have. It's also recommended adding it to the Django admin panel. Edit the content of the `resources/admin.py` file:

```
from rotest.management.admin import register_resource_to_admin

from . import models

register_resource_to_admin(models.CalculatorData, attr_list=['ip_address'])
```

Let's continue to write the Calculator resource, which exposes a simple calculation action. Edit the file `resources/calculator.py`:

```
import rpyc
from rotest.management.base_resource import BaseResource

from .models import CalculatorData

class Calculator(BaseResource):
    DATA_CLASS = CalculatorData

    PORT = 1357

    def connect(self):
        self._rpyc = rpyc.classic.connect(self.data.ip_address, self.PORT)

    def calculate(self, expression):
        return self._rpyc.eval(expression)

    def finalize(self):
```

(continues on next page)

(continued from previous page)

```
if self._rpyc is not None:
    self._rpyc.close()
    self._rpyc = None
```

Note the following:

- There is a use in the RPyC module, which can be installed using:

```
$ pip install rpyc
```

- The `Calculator` class inherits from `rotest.management.base_resource.BaseResource`.
- The previously declared class `CalculatorData` is referenced in this class.
- Two methods are used to set up and tear down the connection to the resource: `rotest.management.base_resource.BaseResource.connect()` and `rotest.management.base_resource.BaseResource.finalize()`.

## Running the Resource Management Server

First, let's initialize the database with the following Django commands:

```
$ python manage.py makemigrations
Migrations for 'resources':
  0001_initial.py:
    - Create model CalculatorData
$ python manage.py migrate
Operations to perform:
  Apply all migrations: core, management, sessions, admin, auth, contenttypes,
↳ resources
Running migrations:
  Applying contenttypes.0001_initial... OK
  Applying auth.0001_initial... OK
  Applying admin.0001_initial... OK
  Applying management.0001_initial... OK
  Applying management.0002_auto_20150224_1427... OK
  Applying management.0003_add_isusable_and_comment... OK
  Applying management.0004_auto_20150702_1312... OK
  Applying management.0005_auto_20150702_1403... OK
  Applying management.0006_delete_projectdata... OK
  Applying management.0007_baseresource_group... OK
  Applying management.0008_add_owner_reserved_time... OK
  Applying management.0009_initialize_timeout_resource... OK
  Applying management.0010_finalize_timeout_resource... OK
  Applying management.0011_refactored_to_resourcedata... OK
  Applying management.0012_delete_previous_resources... OK
  Applying core.0001_initial... OK
  Applying core.0002_auto_20170308_1248... OK
  Applying management.0013_auto_20170308_1248... OK
  Applying resources.0001_initial... OK
  Applying sessions.0001_initial... OK
```

The first command creates a migrations file, that orders changing the database schemas or contents. The second command changes the database according to those orders. If the database does not already exist, it creates it.

Let's run the Rotest server, using the **rotest server** command:

```
$ rotest server

Running in attached mode
Running the Django server as well
<2018-05-23 20:05:26,574>[DEBUG][main@91]: Starting resource manager, port:7777
<2018-05-23 20:05:26,575>[DEBUG][manager@101]: Resource manager main thread started
Performing system checks...

System check identified no issues (0 silenced).
May 23, 2018 - 20:05:28
Django version 1.7.11, using settings 'rotest_demo.settings'
Starting development server at http://0.0.0.0:8000/
Quit the server with CONTROL-C.
```

## Adding a Resource on Django Admin Panel

To sum this up, let's add a Calculator resource. Run the *createsuperuser* command to get access to the admin panel:

```
$ python manage.py createsuperuser
Username (leave blank to use 'user'): <choose a user in here>
Email address: <choose your email address>
Password: <type in your password>
Password (again): <type password again>
Superuser created successfully.
```

Now, Just enter the Django admin panel (via <http://127.0.0.1:8000/admin>), access it using the above credentials, and add a resource with the name `calc` and a local IP address like `127.0.0.1`:

## Writing a Resource-Based Test

In this section, we are going to add a resource request to our existing test. The first thing we need to do, is setting up our resource named `calc`. We need to run the RPyC server of the calculator, using the following command:

```
$ rpyc_classic.py --port 1357
INFO:SLAVE/1357:server started on [0.0.0.0]:1357
```

This way, we have a way to communicate to our resource, which is running on our local computer (or may run on other computer, assuming you've set the corresponding IP address in the Django admin).

Now, let's change the previously written module `test_math.py` with the following content:

```
from rotest import main
from rotest.core import TestCase

from resources.calculator import Calculator

class AddTest(TestCase):
    calc = Calculator()

    def test_add(self):
        result = self.calc.calculate("1 + 1")
        self.assertEqual(result, 2)
```

(continues on next page)

The screenshot shows a web browser window with the address bar displaying `127.0.0.1:8080/admin/resources/calculatordata/add/`. The page title is "Django administration" and the user is logged in as "rotest". The breadcrumb trail is "Home > Resources > Calculator datas > Add calculator data".

The main form is titled "Add calculator data" and contains the following fields:

- Name:** A text input field containing the value "calc".
- Dirty:** A checkbox that is currently unchecked.
- Is usable:** A checkbox that is currently checked.
- Group:** A dropdown menu showing "-----" with a green plus icon to its right.
- Comment:** A text input field.
- Owner:** A text input field.
- Reserved:** A text input field.
- Owner time:** A section containing a "Date:" field with a "Today" button and a calendar icon, and a "Time:" field with a "Now" button and a clock icon. Below these fields is a note: "Note: You are 2 hours ahead of server time."
- Reserved time:** A section containing a "Date:" field with a "Today" button and a calendar icon, and a "Time:" field with a "Now" button and a clock icon. Below these fields is a note: "Note: You are 2 hours ahead of server time."
- Ip address:** A text input field containing the value "127.0.0.1", which is highlighted in yellow.

At the bottom of the form, there are three buttons: "Save and add another", "Save and continue editing", and "Save".

Fig. 1: Adding a resource via Django admin

(continued from previous page)

```
if __name__ == "__main__":
    main()
```

Now, let's run the test:

```
$ python test_math.py
AnonymousSuite
  AddTest.test_add ... OK

Ran 1 test in 0.160s

OK
```

Well done! You've just written your first resource oriented test, that asserts the behaviour of a simple addition of a Calculator resource.

## 1.3 Command Line Options

Let's go over the some of Rotest features, by examining the command line options.

### 1.3.1 Server Options

You can run the server using command **rotest server**. The command by default runs Django's server as well, though it can be disabled.

#### Getting Help

**-h, --help**

Show a help message and exit.

The **--help** option is here to help:

```
$ rotest server --help
Run resource management server.

Usage:
  rotest server [options]

Options:
  -h, --help                Show help message and exit.
  -p <port>, --port <port> Port for communicating with the client.
  --no-django               Skip running the Django web server.
  --django-port <port>     Django's web server port [default: 8000].
  -D, --daemon              Run as a background process.
```

#### Selecting Server's Port

**--port <port>**

Select the port for communicating with the client.

By default, the server uses the specified configuration for the port (see `ROTEST_SERVER_PORT`), or defaults to 7777. If this port is already in use and you'd like to change it, use option **--port**:

```
$ rotest server --port 8888
Running in attached mode
Running the Django server as well
<2018-05-23 19:54:54,550>[DEBUG][main@91]: Starting resource manager, port:8888
<2018-05-23 19:54:54,551>[DEBUG][manager@101]: Resource manager main thread started
Performing system checks...

System check identified no issues (0 silenced).
May 23, 2018 - 19:54:56
Django version 1.7.11, using settings 'rotest_demo.settings'
Starting development server at http://0.0.0.0:8000/
Quit the server with CONTROL-C.
```

### Skip running Django server

#### **--no-django**

Skip running the Django web server.

You can disable running Django server, using option *--no-django*:

```
$ rotest server --no-django
Running in attached mode
<2018-05-23 19:54:54,550>[DEBUG][main@91]: Starting resource manager, port:7777
<2018-05-23 19:54:54,551>[DEBUG][manager@101]: Resource manager main thread started
```

### Selecting Django's Port

#### **--django-port <port>**

Select Django's web server port.

By default, the server uses port 8000 for running Django's server. If you'd like to change it, use option *--django-port*:

```
$ rotest server --django-port 9000
Running in attached mode
Running the Django server as well
<2018-05-23 19:54:54,550>[DEBUG][main@91]: Starting resource manager, port:7777
<2018-05-23 19:54:54,551>[DEBUG][manager@101]: Resource manager main thread started
Performing system checks...

System check identified no issues (0 silenced).
May 23, 2018 - 19:54:56
Django version 1.7.11, using settings 'rotest_demo.settings'
Starting development server at http://0.0.0.0:9000/
Quit the server with CONTROL-C.
```

### Daemon Mode

#### **-D, --daemon**

Run as a daemon process.



**Warning:** Not implemented in Windows.

A common case is to run the server in the background. Use options `--daemon` or `-D` to run the server as a daemon process:

```
$ rotest server --daemon
Running in detached mode (as daemon)
```

## 1.3.2 Client Options

### Running tests

Running tests can be done in the following ways:

- Using the *rotest* command:

```
$ rotest [PATHS]... [OPTIONS]
```

The command can get every path - either files or directories. Every directory will be recursively visited for finding more files. If no path was given, the current working directory will be selected by default.

- Calling the `rotest.main()` function:

```
from rotest import main
from rotest.core import TestCase

class Case(TestCase):
    def test(self):
        pass

if __name__ == "__main__":
    main()
```

Then, this same file can be ran:

```
$ python test_file.py [OPTIONS]
```

### Getting Help

#### **-h, --help**

Show a help message and exit.

If you're not sure what you can do, the help options `-h` and `--help` are here to help:

```
$ rotest -h
Run tests in a module or directory.

Usage:
    rotest [<path>...] [options]

Options:
```

(continues on next page)

(continued from previous page)

```
-h, --help
    Show help message and exit.
--version
    Print version information and exit.
-c <path>, --config <path>
    Test configuration file path.
-s, --save-state
    Enable saving state of resources.
-d <delta-iterations>, --delta <delta-iterations>
    Enable run of failed tests only - enter the number of times the
    failed tests should be run.
-p <processes>, --processes <processes>
    Use multiprocess test runner - specify number of worker
    processes to be created.
-o <outputs>, --outputs <outputs>
    Output handlers separated by comma.
-f <query>, --filter <query>
    Run only tests that match the filter expression,
    e.g. 'Tag1* and not Tag13'.
-n <name>, --name <name>
    Assign a name for current launch.
-l, --list
    Print the tests hierarchy and quit.
-F, --failfast
    Stop the run on first failure.
-D, --debug
    Enter ipdb debug mode upon any test exception.
-S, --skip-init
    Skip initialization and validation of resources.
-r <query>, --resources <query>
    Specify resources to request by attributes,
    e.g. '-r res1.group=QA,res2.comment=CI'.
```

## Listing and Filtering

### **-l, --list**

Print the tests hierarchy and quit.

### **--f <query>, --filter <query>**

Run only tests that match the filter expression, e.g. “Tag1\* and not Tag13”.

Next, you can print a list of all the tests that will be run, using *-l* or *--list* options:

```
$ rotest some_test_file.py -l
CalculatorSuite []
| CasesSuite []
| | PassingCase.test_passing ['BASIC']
| | FailingCase.test_failing ['BASIC']
| | ErrorCase.test_error ['BASIC']
| | SkippedCase.test_skip ['BASIC']
| | SkippedByFilterCase.test_skipped_by_filter ['BASIC']
| | ExpectedFailureCase.test_expected_failure ['BASIC']
| | UnexpectedSuccessCase.test_unexpected_success ['BASIC']
| PassingSuite []
| | PassingCase.test_passing ['BASIC']
| | SuccessFlow ['FLOW']
```

(continues on next page)

(continued from previous page)

```

| | | PassingBlock.test_method
| | | PassingBlock.test_method
| FlowsSuite []
| | FailsAtSetupFlow ['FLOW']
| | | PassingBlock.test_method
| | | FailingBlock.test_method
| | | ErrorBlock.test_method
| | FailsAtTearDownFlow ['FLOW']
| | | PassingBlock.test_method
| | | TooManyLogLinesBlock.test_method
| | | FailingBlock.test_method
| | | ErrorBlock.test_method
| | SuccessFlow ['FLOW']
| | | PassingBlock.test_method
| | | PassingBlock.test_method

```

You can see the tests hierarchy, as well as the tags each test has. Speaking about tags, you can apply filters on the tests to be run, or on the shown list of tests using the `-f` or `--filter` options:

```

$ rotest some_test_file.py -f FLOW -l
CalculatorSuite []
| CasesSuite []
| | PassingCase.test_passing ['BASIC']
| | FailingCase.test_failing ['BASIC']
| | ErrorCase.test_error ['BASIC']
| | SkippedCase.test_skip ['BASIC']
| | SkippedByFilterCase.test_skipped_by_filter ['BASIC']
| | ExpectedFailureCase.test_expected_failure ['BASIC']
| | UnexpectedSuccessCase.test_unexpected_success ['BASIC']
| PassingSuite []
| | PassingCase.test_passing ['BASIC']
| | SuccessFlow ['FLOW']
| | | PassingBlock.test_method
| | | PassingBlock.test_method
| FlowsSuite []
| | FailsAtSetupFlow ['FLOW']
| | | PassingBlock.test_method
| | | FailingBlock.test_method
| | | ErrorBlock.test_method
| | FailsAtTearDownFlow ['FLOW']
| | | PassingBlock.test_method
| | | TooManyLogLinesBlock.test_method
| | | FailingBlock.test_method
| | | ErrorBlock.test_method
| | SuccessFlow ['FLOW']
| | | PassingBlock.test_method
| | | PassingBlock.test_method

```

The output will be colored in a similar way as above.

You can include boolean literals like `not`, `or` and `and` in your filter, as well as using test names and wildcards (all non-literals are case insensitive):

```

$ rotest some_test_file.py -f "basic and not skipped*" -l
CalculatorSuite []
| CasesSuite []

```

(continues on next page)

(continued from previous page)

		PassingCase.test_passing ['BASIC']
		FailingCase.test_failing ['BASIC']
		ErrorCase.test_error ['BASIC']
		SkippedCase.test_skip ['BASIC']
		SkippedByFilterCase.test_skipped_by_filter ['BASIC']
		ExpectedFailureCase.test_expected_failure ['BASIC']
		UnexpectedSuccessCase.test_unexpected_success ['BASIC']
		PassingSuite []
		PassingCase.test_passing ['BASIC']
		SuccessFlow ['FLOW']
		PassingBlock.test_method
		PassingBlock.test_method
		FlowsSuite []
		FailsAtSetupFlow ['FLOW']
		PassingBlock.test_method
		FailingBlock.test_method
		ErrorBlock.test_method
		FailsAtTearDownFlow ['FLOW']
		PassingBlock.test_method
		TooManyLogLinesBlock.test_method
		FailingBlock.test_method
		ErrorBlock.test_method
		SuccessFlow ['FLOW']
		PassingBlock.test_method
		PassingBlock.test_method

## Stopping at first failure

### **-F, --failfast**

Stop the run on first failure.

The *-F* or *--failfast* options can stop execution after first failure:

```
$ rotest some_test_file.py --failfast
CalculatorSuite
CasesSuite
  PassingCase.test_passing ... OK
  FailingCase.test_failing ... FAIL
Traceback (most recent call last):
  File "/home/odp/code/rotest/src/rotest/core/case.py", line 310, in test_method_
↪wrapper
    test_method(*args, **kwargs)
  File "tests/calculator_tests.py", line 34, in test_failing
    self.assertEqual(1, 2)
AssertionError: 1 != 2

=====
FAIL: FailingCase.test_failing
-----
Traceback (most recent call last):
  File "/home/odp/code/rotest/src/rotest/core/case.py", line 310, in test_method_
↪wrapper
    test_method(*args, **kwargs)
  File "tests/calculator_tests.py", line 34, in test_failing
```

(continues on next page)

(continued from previous page)

```

    self.assertEqual(1, 2)
AssertionError: 1 != 2

Ran 2 tests in 0.205s

FAILED (failures=1)

```

## Debug Mode

### `-D`, `--debug`

Enter `ipdb` debug mode upon any test exception.

The `-D` or `--debug` options can enter debug mode when exceptions are raised at the top level of the code:

```

$ rotest some_test_file.py --debug
AnonymousSuite
  FailingCase.test ...
Traceback (most recent call last):
  File "tests/some_test_file.py", line 11, in test
    self.assertEqual(self.calculator.calculate("1+1"), 3)
  File "/usr/lib64/python2.7/unittest/case.py", line 513, in assertEquals
    assertion_func(first, second, msg=msg)
  File "/usr/lib64/python2.7/unittest/case.py", line 506, in _baseAssertEqual
    raise self.failureException(msg)
AssertionError: 2.0 != 3
> tests/some_test_file.py(12)test()
   10     def test(self):
   11         self.assertEqual(self.calculator.calculate("1+1"), 3)
--> 12
   13
   14 if __name__ == "__main__":

ipdb> help

Documented commands (type help <topic>):
=====
EOF      c          d          help      longlist  pinfo      raise      tbreak    whatis
a        cl        debug      ignore    n         pinfo2     restart    u          where
alias    clear     disable    j         next      pp         retry      unalias
args     commands down      jump      p         psource    return     unt
b        condition enable    l         pdef      q         run        until
break    cont      exit      list      pdoc      quit       s          up
bt       continue h         ll        pfile     r         step       w

```

Once in the debugging session, you can do any of the following:

- Inspect the situation, by evaluating expressions or using commands that are supported by `ipdb`. For example: continuing the flow, jumping into a specific line, etc.
- `retry` the action, if it's a known flaky action and someone's going to take care of it soon.
- `raise` the exception, and failing the test.

## Retrying Tests

**-d** <delta-iterations>, **--delta** <delta-iterations>  
 Rerun test a specified amount of times until it passes.

In case you have flaky tests, you can automatically rerun a test until getting a success result. Use options **--delta** or **-d**:

```
$ rotest some_test_file.py --delta 2
AnonymousSuite
  FailingCase.test ... FAIL
Traceback (most recent call last):
  File "rotest/src/rotest/core/case.py", line 310, in test_method_wrapper
    test_method(*args, **kwargs)
  File "some_test_file.py", line 11, in test
    self.assertEqual(self.calculator.calculate("1+1"), 3)
AssertionError: 2.0 != 3

=====
FAIL: FailingCase.test
-----
Traceback (most recent call last):
  File "rotest/src/rotest/core/case.py", line 310, in test_method_wrapper
    test_method(*args, **kwargs)
  File "some_test_file.py", line 11, in test
    self.assertEqual(self.calculator.calculate("1+1"), 3)
AssertionError: 2.0 != 3

Ran 1 test in 0.122s

FAILED (failures=1)
AnonymousSuite
  FailingCase.test ... OK

Ran 1 test in 0.082s

OK
```

## Running Tests in Parallel

**-p** <processes>, **--processes** <processes>  
 Spawn specified amount of processes to execute tests.

To optimize the running time of tests, you can use options **-p** or **--processes** to run several work processes that can run tests separately.

Any test have a `TIMEOUT` attribute (defaults to 30 minutes), and it will be enforced only when spawning at least one worker process:

```
class SomeTest(TestCase):
    # Test will stop if it exceeds execution time of an hour,
    # only when the number of processes spawned is greater or equal to 1
    TIMEOUT = 60 * 60

    def test(self):
        pass
```

## Specifying Resources to Use

**-r <query>, --resources <query>**  
Choose resources based on the given query.

You can run tests with specific resources, using options `--resources` or `-r`.

The request is of the form:

```
$ rotest some_test_file.py --resources <query-for-resource-1>,<query-for-resource-2>,.
↪ ..
```

As an example, let's suppose we have the following test:

```
class SomeTest(TestCase):
    res1 = Resource1()
    res2 = Resource2()

    def test(self):
        ...
```

You can request resources by their names:

```
$ rotest some_test_file.py --resources res1=name1,res2=name2
```

Alternatively, you can make more complex queries:

```
$ rotest some_test_file.py --resources res1.group.name=QA,res2.comment=nightly
```

## Activating Output Handlers

**-o <outputs>, --outputs <outputs>**

To activate an output handler, use options `-o` or `--outputs`, with the output handlers separated using commas:

```
$ rotest some_test_file.py --outputs excel,logdebug
```

For more about output handlers, read on [Output Handlers](#).

## 1.4 Output Handlers

Output Handlers are a great concept in Rotest. They let you take actions when certain events occurs, as a logic separated from the test's logic.

Rotest has several builtin output handlers, as well as enable making custom output handlers.

### 1.4.1 Dots

The most compact way to display results - using one character per test:

```
$ python some_test_file.py -o dots
.FEssxu.....FsF..FEE...

...
```

Based on the following legend:

.	Success
F	Failure
E	Error
s	Skip
x	Expected Failure
u	Unexpected Success

## 1.4.2 Full

If you want to just be aware of every event, use the `full` output handler:

```
$ python some_test_file.py -o full
Tests Run Started
Test CalculatorSuite Started
Test CasesSuite Started
Test PassingCase.test_passing Started
Success: test_passing (__main__.PassingCase)
Test PassingCase.test_passing Finished
Test FailingCase.test_failing Started
Failure: test_failing (__main__.FailingCase)
Traceback (most recent call last):
  File "rotest/src/rotest/core/case.py", line 310, in test_method_wrapper
    test_method(*args, **kwargs)
  File "tests/calculator_tests.py", line 34, in test_failing
    self.assertEqual(1, 2)
AssertionError: 1 != 2

Test FailingCase.test_failing Finished
Test ErrorCase.test_error Started
Error: test_error (__main__.ErrorCase)
Traceback (most recent call last):
  File "rotest/src/rotest/core/case.py", line 310, in test_method_wrapper
    test_method(*args, **kwargs)
  File "tests/calculator_tests.py", line 44, in test_error
    1 / 0
ZeroDivisionError: integer division or modulo by zero

...
```

## 1.4.3 Tree

For a tree view, use:

```
$ python some_test_file.py -o tree
CalculatorSuite
  CasesSuite
    PassingCase.test_passing ... OK
    FailingCase.test_failing ... FAIL
    Traceback (most recent call last):
      File "/home/odp/code/rotest/src/rotest/core/case.py", line 310, in test_method_
↪rapper
        test_method(*args, **kwargs)
```

(continues on next page)



(continued from previous page)

```

File "tests/calculator_tests.py", line 34, in test_failing
    self.assertEqual(1, 2)
AssertionError: 1 != 2

ErrorCase.test_error ... ERROR
Traceback (most recent call last):
  File "/home/odp/code/rotest/src/rotest/core/case.py", line 310, in test_method_
↪wrapper
    test_method(*args, **kwargs)
  File "tests/calculator_tests.py", line 44, in test_error
    1 / 0
ZeroDivisionError: integer division or modulo by zero

...

```

### 1.4.4 Logs

To see the logs while running the tests, use `logdebug` or `loginfo`. Additionally, you can use `pretty` for an easier to read logging system. As expected, `logdebug` will print every log record with level which is higher or equal to `DEBUG` (`DEBUG`, `INFO`, `WARNING`, `ERROR`, `CRITICAL`), whereas `loginfo` will print every log record with level which is higher or equal to `INFO` (`INFO`, `WARNING`, `ERROR`, `CRITICAL`).

### 1.4.5 XML & Excel

Sometimes, you want to have a better visualization of the results. Rotest can output the results into a human-readable `results.xls` file, which can be sent via email for instance. Alternatively, it can output a Junit-compatible XML, which lots of reporting systems can parse and display. The two relevant options are `-o excel` and `-o xml`.

Those artifacts are saved in the working directory of Rotest. For more about this location, see [Configurations](#).

### 1.4.6 Remote

When adding `remote` to the list of output handlers, all test events and results are saved in the remote (server's) database, which enables keeping tests run history. Furthermore, tests skip delta filtering (`--delta` run option) queries the remote database to see which tests already passed.

### 1.4.7 DB

The `db` handler behaves the same as `remote` handler, only uses a local DB (which should be defined in your project's `settings.py` file)

### 1.4.8 Artifact

This handler saves the working directory of the tests into a ZIP file, which might be useful for keeping important runs' logs and other files for future debugging or evaluation.

Those artifacts are saved in the artifacts directory of Rotest. It is recommended to make this folder a shared folder between all your users. For more about this location, see [Configurations](#).

## 1.5 Configurations

Rotest behaviour can be configured in the following ways:

- A configuration file called `rotest.yml` in YAML format.
- Environment variables.
- Command line arguments.

Each way has its own advantages, and should be used in different occasions: configuration file fits where some configuration should be used by any user of the code, environment variables should be specific per user or maybe more session-based, and command line arguments are relevant for a specific run.

---

**Note:** In general:

- Command line arguments take precedence over environment variables.
  - Environment variables take precedence over the configuration file.
  - Some configuration attributes have default values, in case there's no answer.
- 

### 1.5.1 General

To use a configuration file, put any of the following path names in the project's root directory: `rotest.yml`, `rotest.yaml`, `.rotest.yml`, `.rotest.yaml`.

The configuration file is of the form:

```
rotest:
  attribute1: value1
  attribute2: value2
```

You can configure environment variables this way in Linux / Mac / any Unix machine:

```
$ export ENVIRONMENT_VARIABLE=value
```

and this way in Windows:

```
$ set ENVIRONMENT_VARIABLE=value
$ setx ENVIRONMENT_VARIABLE=value # Set it permanently (reopen the shell)
```

### 1.5.2 Working Directory

#### **ROTEST\_WORK\_DIR**

Working directory to save artifacts to.

Rotest uses the computer's storage in order to save several artifacts. You can use the following methods:

- Define `ROTEST_WORK_DIR` to point to the path.
- Define `workdir` in the configuration file:

```
rotest:
  workdir: /home/user/workdir
```

- Use the default, which is `~/ .rotest` or `%HOME%\ .rotest` in Windows.

### 1.5.3 Host

#### ROTEST\_HOST

DNS or IP address to the Rotest's server.

Rotest is built on a client-server architecture. To define the relevant server that the client should contact with, use the following methods:

- Define `ROTEST_HOST` to point to the server DNS or IP address.
- Define `host` in the configuration file:

```
rotest:
    host: rotestserver
```

- Use the default, which is `localhost`.

### 1.5.4 Port

#### ROTEST\_SERVER\_PORT

Port on the server's side, to be used for communication with clients.

To define the relevant server's port the will be opened, and the port clients will communicate with, use the following methods:

- Define `ROTEST_SERVER_PORT` with the desired port.
- Define `port` in the configuration file:

```
rotest:
    port: 8585
```

- Use the default, which is `7777`.

### 1.5.5 Resource Request Timeout

#### ROTEST\_RESOURCE\_REQUEST\_TIMEOUT

Amount of time to wait before deciding that no resource is available.

Rotest's server distributes resources to multiple clients. Sometimes, a client cannot get some of the resources at the moment, so the server returns an answer that there's no resource available. This amount of time is configurable via the following methods:

- Define `ROTEST_RESOURCE_REQUEST_TIMEOUT` with the number of seconds to wait before giving up on waiting for resources.
- Define `resource_request_timeout` in the configuration file:

```
rotest:
    resource_request_timeout: 60
```

- Use the default, which is `0` (not waiting at all).

### 1.5.6 Django Settings Module

#### DJANGO\_SETTINGS\_MODULE

Django configuration path, in a module syntax.

Rotest is a Django library, and as such needs its configuration module, in order to write and read data about the resources from the database. Define it in the following ways:

- Define `DJANGO_SETTINGS_MODULE`.
- Define `django_settings` in the configuration file:

```
rotest:
    django_settings: package1.package2.settings
```

- There is no default value.

### 1.5.7 Artifacts Directory

#### **ARTIFACTS\_DIR**

Rotest artifact directory.

Rotest enables saving ZIP files containing the tests and resources data, using an output handler named `artifact` (see *Output Handlers*). Define it in the following ways:

- Define `ARTIFACTS_DIR`.
- Define `artifact_dir` in the configuration file:

```
rotest:
    artifacts_dir: ~/rotest_artifacts
```

- Use the default, which is `~/rotest/artifacts`.

### 1.5.8 Shell Apps

`rotest shell` automatically attempts to load resources classes into the environment to save the user the need to do so. Define the default rotest applications to be loaded in the following ways:

- Define `shell_apps` in the configuration file:

```
rotest:
    shell_apps: ["resources", "tools"]
```

- Use the default, which is `[]`.

### 1.5.9 Shell Startup Commands

`rotest shell` enables defining startup commands, to save the user the need to write them every time. The commands must be simple one-liners. Define it in the following ways:

- Define `shell_startup_commands` in the configuration file:

```
rotest:
    shell_startup_commands: ["from tests.blocks import *"]
```

- Use the default, which is `[]`.

### 1.5.10 Discoverer Blacklist

Rotest enables loading resources from an app, a thing that happens automatically when running “rotest shell”, but some files can / must be skipped when searching for the resources. The methods (under `rotest.management.utils.resources_discoverer`) do get a *blacklist* argument, but the default value is extracted from the config.

Define it in the following ways:

- Define `discoverer_blacklist` in the configuration file:

```
rotest:
    discoverer_blacklist: ["*/scripts/*", "*static.py"]
```

- Use the default, which is `[]`.



## 2.1 Adding Custom Output Handlers

### 2.1.1 Third Party Output Handlers

- `rotest_reportportal`
  - Plugin to the amazing [Report Portal](#) system, that enables viewing test results and investigating them.

### 2.1.2 How to Make Your Own Output Handler

You can make your own Output Handler, following the next two steps:

- Inheriting from `rotest.core.result.handlers.abstract_handler.AbstractResultHandler`, and overriding the relevant methods.
- Register the above inheriting class as an entrypoint, in a `setup.py` file, and make sure it's being install on the environment.

For an example, please refer to `rotest_reportportal` plugin.

### 2.1.3 Available Events

The available methods of an output handler:

```
class rotest.core.result.handlers.abstract_handler.AbstractResultHandler (main_test=None,  
                                                                    *args,  
                                                                    **kwargs)
```

Result handler interface.

Defines the required interface for all the result handlers.

**main\_test**

*rotest.core.abstract\_test.AbstractTest* – the main test instance (e.g. *TestSuite* instance or *TestFlow* instance).

**add\_error** (*test*, *exception\_string*)

Called when an error has occurred.

**Parameters**

- **test** (*rotest.core.abstract\_test.AbstractTest*) – test item instance.
- **exception\_string** (*str*) – exception description.

**add\_expected\_failure** (*test*, *exception\_string*)

Called when an expected failure/error occurred.

**Parameters**

- **test** (*rotest.core.abstract\_test.AbstractTest*) – test item instance.
- **exception\_string** (*str*) – exception description.

**add\_failure** (*test*, *exception\_string*)

Called when an error has occurred.

**Parameters**

- **test** (*rotest.core.abstract\_test.AbstractTest*) – test item instance.
- **exception\_string** (*str*) – exception description.

**add\_skip** (*test*, *reason*)

Called when a test is skipped.

**Parameters**

- **test** (*rotest.core.abstract\_test.AbstractTest*) – test item instance.
- **reason** (*str*) – reason for skipping the test.

**add\_success** (*test*)

Called when a test has completed successfully.

**Parameters** **test** (*rotest.core.abstract\_test.AbstractTest*) – test item instance.

**add\_unexpected\_success** (*test*)

Called when a test was expected to fail, but succeed.

**Parameters** **test** (*rotest.core.abstract\_test.AbstractTest*) – test item instance.

**print\_errors** (*tests\_run*, *errors*, *skipped*, *failures*, *expected\_failures*, *unexpected\_successes*)

Called by *TestRunner* after test run.

**Parameters**

- **tests\_run** (*number*) – count of tests that has been run.
- **errors** (*list*) – error tests details list.
- **skipped** (*list*) – skipped tests details list.
- **failures** (*list*) – failed tests details list.
- **expected\_failures** (*list*) – expected-to-fail tests details list.
- **unexpected\_successes** (*list*) – unexpected successes tests details list.



**setup\_finished** (*test*)

Called when the given test finished setting up.

**Parameters** **test** (*rotest.core.abstract\_test.AbstractTest*) – test item instance.

**should\_skip** (*test*)

Check if the test should be skipped.

**Parameters** **test** (*rotest.core.abstract\_test.AbstractTest*) – test item instance.

**Returns** skip reason if the test should be skipped, None otherwise.

**Return type** *str*

**start\_composite** (*test*)

Called when the given TestSuite is about to be run.

**Parameters** **test** (*rotest.core.suite.TestSuite*) – test item instance.

**start\_teardown** (*test*)

Called when the given test is starting its teardown.

**Parameters** **test** (*rotest.core.abstract\_test.AbstractTest*) – test item instance.

**start\_test** (*test*)

Called when the given test is about to be run.

**Parameters** **test** (*rotest.core.abstract\_test.AbstractTest*) – test item instance.

**start\_test\_run** ()

Called once before any tests are executed.

**stop\_composite** (*test*)

Called when the given TestSuite has been run.

**Parameters** **test** (*rotest.core.suite.TestSuite*) – test item instance.

**stop\_test** (*test*)

Called when the given test has been run.

**Parameters** **test** (*rotest.core.abstract\_test.AbstractTest*) – test item instance.

**stop\_test\_run** ()

Called once after all tests are executed.

**update\_resources** (*test*)

Called once after locking the tests resources.

**Parameters** **test** (*rotest.core.abstract\_test.AbstractTest*) – test item instance.

## 2.2 Blocks code architecture

### 2.2.1 Background

The blocks design paradigm was created to avoid code duplication and enable composing tests faster.

`TestBlock` is a building block for tests, commonly responsible for a single action or a small set of actions. It inherits from `unittest`’s `TestCase`, enabling it test-like behavior (`self.skipTest`, `self.assertEqual`, `self.fail`, etc.), and the Rotest infrastructure expands its behavior to also be function-like (to have “inputs” and “outputs”).

`TestFlow` is a test composed of `TestBlock` instances (or other sub-test flows), passing them their ‘inputs’ and putting them together, enabling them to share data between each other. A `TestFlow` can lock resources much like Rotest’s `TestCase`, which it passes to all the blocks under it.

The flow’s final result depends on the result of the blocks under it by the following order:

- If some block had an error, the flow ends with an error.
- If some block had a failure, the flow ends with a failure.
- Otherwise, the flow succeeds.

See also `mode` in the `TestBlock`’s “Features” segment below for more information about the run mechanism of a `TestFlow`.

## 2.2.2 Features

### TestFlow

1. **blocks:** static list or tuple of the blocks’ classes of the flow. You can parametrize blocks in this section, in order to pass data to them (see [Sharing data](#) section or explanation in the `TestBlock` features section).
2. Rotest’s `TestCase` features: `run delta`, filter by tags, running in `multiprocess`, `TIMEOUT`, etc. are available also for `TestFlow` class.

### TestBlock

1. **inputs:** define class fields and assign them to instances of `BlockInput` to ask for values for the block (values are passed via `common`, `parametrize`, previous blocks passing them as `outputs`, or as requested resources of the block or its containers). You can define a default value to `BlockInput` to assign if non is supplied (making it an optional input). For example, defining in the block’s scope

```
from rotest.core import TestBlock, BlockInput
class DemoBlock(TestBlock):
    field_name = BlockInput()
    other_field = BlockInput(default=1)
    ...
```

will validate that the block instance will have a value for ‘field\_name’ before running the parent flow (and unless another value is supplied, set for the block’s instance: `self.other_field=1`).

2. **outputs:** define class fields and assign them to instances of `BlockOutput` to share values from the instance (`self`) to the parent and siblings. the block automatically shares the declared outputs after teardown. For example, defining in the block’s scope

```
from rotest.core import TestBlock, BlockOutput
class DemoBlock(TestBlock):
    field_name = BlockOutput()
    other_field = BlockOutput()
    ...
```

means declaring that the block would calculate a values for `self.field_name` and `self.other_field` and share them (which happens automatically after its teardown), so that components following the block can use those fields. Declaring inputs and outputs of blocks is not mandatory, but it's a good way to make sure that the blocks "click" together properly, and no block will be missing fields at runtime.

### Common features (for both flows and blocks)

1. `resources`: you can specify resources for the test flow or block, just like in Rotest's `TestCase` class. The resources of a flow will automatically propagate to the components under it.
2. `common`: used to set values to blocks or sub-flows, see example in the [Sharing data](#) section.
3. `parametrize` (also `params`): used to pass values to blocks or sub-flows, see example in the [Sharing data](#) section. Note that calling `parametrize()` or `params()` doesn't actually instantiate the component, but just create a copy of the class and sends the parameters to its `common` (overriding previous values).
4. `mode`: this field can be defined statically in the component's class or passed to the instance using 'parametrize' (parametrized fields override class fields of blocks, since they are injected into the instance). Blocks and sub-flows can run in one of the following modes (which are defined in `rotest.core.flow_component`)
  - (a) `MODE_CRITICAL`: upon failure or error, end the flow's run, skipping the following components (except those with mode `MODE_FINALLY`). Use this mode for blocks or sub-flows that do actions that are mandatory for the continuation of the test.
  - (b) `MODE_OPTIONAL`: upon error only, end the flow's run, skipping the following components (except those with mode `MODE_FINALLY`). Use this mode for block or sub-flows that are not critical for the continuation of the test (since a failure in them doesn't stop the flow).
  - (c) `MODE_FINALLY`: components with this mode aren't skipped even if the flow has already failed and stopped. Upon failure or error, end the flow's run, skipping the following components (except those with mode `MODE_FINALLY`). Use this mode for example in blocks or sub-flows that do cleanup actions (which we should always attempt), much like things you would normally put in 'tearDown' of tests.
5. `request_resources`: blocks and flows can dynamically request resources, calling `request_resources(requests)` method (see Rotest tutorial and documentation for more information).

Since those are dynamic requests, don't forget to release those resources when they are not needed by calling

```
release_resources(
    <dict of the dynamically locked resources, name: instance>)
```

Resources can be locked locally and globally in regarding to the containing flow, i.e. by locking the resources using the parent's method:

```
self.parent.request_resources(requests)
```

The parent flow and all the sibling components would also have them.

### Sharing data

Sharing data between blocks (getting inputs and passing outputs) is crucial to writing simple, manageable, and independent blocks. Passing data to blocks (for them to use as 'inputs' parameters for the block's run, much like arguments for a function) can be done in one of the following methods:

- Locking resources - the resources the flow locks are injected into its components' instances (note that blocks can also lock resources, but they don't propagate them up or down). E.g. if a flow locks a resource with name 'res1', then all its components would have the field 'res1' which points to the locked resource.

- Declaring outputs - see TestBlock's outputs above.
- Setting initial data to the test - you can set initial data to the component and its sub-components by writing:

```
class DemoFlow(TestFlow):
    common = {'field_name': 5,
              'other_field': 'abc'}
    ...
```

This will inject `field_name=5` and `other_field='abc'` as fields of the flow and its components before starting its run, so the blocks would also have access to those fields. Note that you can also declare a `common` dict for blocks, but it's generally recommended to use default values for inputs instead.

- Using `parametrize` - you can specify fields for blocks or flows by calling their 'parametrize' or 'params' class method.

For example:

```
class DemoFlow(TestFlow):
    blocks = (DemoBlock,
              DemoBlock.parametrize(field_name=5,
                                    other_field='abc'))
```

will create two blocks under the `DemoFlow`, one `DemoBlock` block with the default values for `field_name` and `other_field` (which can be set by defining them as class fields for the block for example, see optional inputs and fields section), and a second `DemoBlock` with `field_name=5` and `other_field='abc'` injected into the block instance (at runtime).

Regarding priorities hierarchy between the methods, it follows two rules:

1. For a single component, calling `parametrize` on it overrides the values set through `common`.
2. `common` and `parametrize` of sub-components are stronger than the values passed by containing hierarchies. E.g. `common` values of a flow are of lower priority than the `parametrize` values passed to the blocks under it.

## Example

```
from rotest.core import TestBlock, BlockInput, BlockOutput
class DoSomethingBlock(TestBlock):
    """A block that does something.

    Attributes:
        resource1 (object): resource the block uses.
        input2 (object): input for the block.
        optional3 (object): optional input for the block.
    """
    mode = MODE_CRITICAL

    resource1 = BlockInput()
    input2 = BlockInput()
    optional3 = BlockInput(default=0)

    output1 = BlockOutput()

    def test_method(self):
        """Do something."""
        self.logger.info("Doing something")
```

(continues on next page)

(continued from previous page)

```

        value = self.resource1.do_something(self.input2, self.optional3)
        self.output1 = value * 5 # This will be shared with siblings
    ...

class DemoFlow(TestFlow):
    """Demo test-flow."""
    resource1 = SomeResourceClass(some_limitation=LIMITATION)

    common = {'input2': INPUT_VALUE}

    blocks = (DemoBlock1,
              DemoBlock2,
              DemoBlock1,
              DoSomethingBlock.params(optional3=5),
              DoSomethingBlock,
              DemoBlock1.params(mode=MODE_FINALLY))

```

## Sub-flows

A flow may contain not only test-block, but also test-flows under it. This feature can be used to wrap together blocks that tend to come together and also to create sub-procedures (if a test block is comparable to a simple function - it may have inputs and outputs and does a simple action, then a sub-flow can be considered a complex function, which invokes other simpler functions). Note that a sub-flow behaves exactly like a block, meaning, you can call `parametrize` on it, set a mode to it, it can't be filtered or skipped with `delta`, etc. This can give extra flexibility when composing flows with complex scenarios, for example:

```

Flow
|__BlockA
|__BlockB
|__BlockC
|__BlockD

```

If you want that block B will only run if block A passed, and that block D will only run if block C passed, but also to keep A and C not dependent, doing so is impossible without the usage of sub flows. But the scenario can be coded in the following manner:

```

Flow
|__SubFlow1 (mode optional)
|   |__BlockA (mode critical)
|   |__BlockB (mode critical)
|__SubFlow2 (mode optional)
|   |__BlockC (mode critical)
|   |__BlockD (mode critical)

```

## Anonymous test-flows

Sub-flows can be created on-the-spot using the `'create_flow'` function, to avoid defining classes. The function gets the following arguments:

- `blocks` - list of the flow's components.
- `name` - name of the flow, default value is "AnonymousTestFlow", but it's recommended to override it.

- `mode` - mode of the new flow. Either `MODE_CRITICAL`, `MODE_OPTIONAL` or `MODE_FINALLY`. Default is `MODE_CRITICAL`.
- `common` - dict of initial fields and values for the new flow, same as the class variable `'common'`, default is empty dict.

```
from rotest.core.flow import TestFlow, create_flow

class DemoFlow(TestFlow):
    """Demo test-flow."""
    resource1 = SomeResourceClass(some_limitation=LIMITATION)

    blocks = (DemoBlock1,
              DemoBlock2,
              DemoBlock1,
              create_flow(name="TestSomethingFlow",
                          common={"input2": "value1"},
                          mode=MODE_OPTIONAL,
                          blocks=[DoSomethingBlock,
                                DoSomethingBlock.params(optional3=5)]),
              create_flow(name="TestSomethingFlow",
                          common={"input2": "value2"},
                          mode=MODE_OPTIONAL,
                          blocks=[DoSomethingBlock,
                                DoSomethingBlock.params(optional3=5)]),
              DemoBlock1.params(mode=MODE_FINALLY))
```

## CHAPTER 3

---

### Indices and tables

---

- `genindex`
- `modindex`
- `search`





## Symbols

-django-port <port>  
     rotest-server command line option, 12  
 -no-django  
     rotest-server command line option, 12  
 -port <port>  
     rotest-server command line option, 11  
 -D, -daemon  
     rotest-server command line option, 12  
 -D, -debug  
     rotest command line option, 17  
 -F, -failfast  
     rotest command line option, 16  
 -d <delta-iterations>, -delta <delta-iterations>  
     rotest command line option, 18  
 -f <query>, -filter <query>  
     rotest command line option, 14  
 -h, -help  
     rotest command line option, 13  
     rotest-server command line option, 11  
 -l, -list  
     rotest command line option, 14  
 -o <outputs>, -outputs <outputs>  
     rotest command line option, 19  
 -p <processes>, -processes <processes>  
     rotest command line option, 18  
 -r <query>, -resources <query>  
     rotest command line option, 19

## A

AbstractResultHandler (class in rotest command line option  
     rotest.core.result.handlers.abstract\_handler), 27  
 add\_error() (rotest.core.result.handlers.abstract\_handler.AbstractResultHandler  
     method), 28  
 add\_expected\_failure() (rotest.core.result.handlers.abstract\_handler.AbstractResultHandler  
     method), 28  
 add\_failure() (rotest.core.result.handlers.abstract\_handler.AbstractResultHandler  
     method), 28

add\_skip() (rotest.core.result.handlers.abstract\_handler.AbstractResultHandler  
     method), 28  
 add\_success() (rotest.core.result.handlers.abstract\_handler.AbstractResultHandler  
     method), 28  
 add\_unexpected\_success()  
     (rotest.core.result.handlers.abstract\_handler.AbstractResultHandler  
     method), 28  
 ARTIFACTS\_DIR, 24

## D

DJANGO\_SETTINGS\_MODULE, 24

## E

environment variable  
     ARTIFACTS\_DIR, 24  
     DJANGO\_SETTINGS\_MODULE, 23, 24  
     ROTEST\_HOST, 23  
     ROTEST\_RESOURCE\_REQUEST\_TIMEOUT, 23  
     ROTEST\_SERVER\_PORT, 11, 23  
     ROTEST\_WORK\_DIR, 22

## M

main\_test (rotest.core.result.handlers.abstract\_handler.AbstractResultHandler  
     attribute), 27

## P

print\_errors() (rotest.core.result.handlers.abstract\_handler.AbstractResultHandler  
     method), 28

## R

-D, -debug, 17  
 -d <delta-iterations>, -delta <delta-iterations>, 18  
 -f <query>, -filter <query>, 14  
 -h, -help, 13  
 -o <outputs>, -outputs <outputs>, 19  
 -p <processes>, -processes <processes>, 18

-r <query>, -resources <query>, 19  
rotest-server command line option  
-django-port <port>, 12  
-no-django, 12  
-port <port>, 11  
-D, -daemon, 12  
-h, -help, 11  
ROTEST\_HOST, 23  
ROTEST\_RESOURCE\_REQUEST\_TIMEOUT, 23  
ROTEST\_SERVER\_PORT, 11, 23  
ROTEST\_WORK\_DIR, 22

## S

setup\_finished() (rotest.core.result.handlers.abstract\_handler.AbstractResultHandler  
method), 28  
should\_skip() (rotest.core.result.handlers.abstract\_handler.AbstractResultHandler  
method), 29  
start\_composite() (rotest.core.result.handlers.abstract\_handler.AbstractResultHandler  
method), 29  
start\_tearardown() (rotest.core.result.handlers.abstract\_handler.AbstractResultHandler  
method), 29  
start\_test() (rotest.core.result.handlers.abstract\_handler.AbstractResultHandler  
method), 29  
start\_test\_run() (rotest.core.result.handlers.abstract\_handler.AbstractResultHandler  
method), 29  
stop\_composite() (rotest.core.result.handlers.abstract\_handler.AbstractResultHandler  
method), 29  
stop\_test() (rotest.core.result.handlers.abstract\_handler.AbstractResultHandler  
method), 29  
stop\_test\_run() (rotest.core.result.handlers.abstract\_handler.AbstractResultHandler  
method), 29

## U

update\_resources() (rotest.core.result.handlers.abstract\_handler.AbstractResultHandler  
method), 29